

HMI Touch color Baseline CH-HP-CR

Changes history

Release 1.18 03-11-2021

- Fan page modified with 2 fan of two circuit
- Desktop modify, with wateroutlet and waterinlet if regulation probe is inlet or outlet. Moved also SET button on the left of setpoint
- Added Low temperature differential parameter 01.218

Release 1.17 24-05-2021

- Fixed dead zone circuit 2 in setpoint page.

Release 1.14 10-05-2021

- Fixed missing alarm code in alarm page (Removed the "Sets" to save code space and use a dedicated script)
- Fixed missing alarm code in history page
- Fixed circuit 2 compressors in compressors page.


Release 1.12/13 7-05-2020

- Changed IO Configuration Page. Removed the "Sets" to save code space and use a dedicated script.


Release 1.11 13-01-2020

CHANGES:

- Changed Alarms page, added Alarm History button and fixed 2nd line description.



- Added Alarms History



- Added Generic Regulator custom description

- Improve HMI reaction by changing on timer script of the main page.
- Aligned with PLC application 2.7.15

```
Used code size:      680B0h (  416 KByte)
Free code space:     4FF50h (  319 KByte)
Total code space:    B8000h (  736 KByte)

Aux area 1 used space:  27E80h (  159 KByte)
Aux area 1 free space:  2D8180h ( 2912 KByte)
Aux area 1 total space: 300000h ( 3072 KByte)

Used data space:      12FD8h (   75 KByte)
Free data space:       828h (    2 KByte)
Total data space:     13800h (   78 KByte)
```

KNOW ISSUE: To update the application a fresh bios upload is needed. Issue under investigation

Release 1.10 26-09-2020

CHANGES: Fied IO IO visualizzation issue

Release 1.07 26-05-2020

CHANGES:

- Aligned with PLC application 2.7.8
- Fixed Compressor Timeout alarms
- Added dead zone in quick set page
- Added Alarm configuration option
- Changed user account from level 1 to level 2 (Level 1 id the guest user)
- Changed user account from level 2 to level 3

Release 1.06 13-05-2020

CHANGES:

- Aligned with PLC application 2.7.6
- Added Compressor Working Hour alarm

Release 1.04 29-04-2020

CHANGES:

- Aligned with PLC application 2.7.4
- Removed Wizard Page
- Review Compressor Page

The screenshot shows the 'Cir1-Compr.1' control panel. At the top, there is a green header bar with the title 'Cir1-Compr.1' and two zeros. Below the header, there are several status indicators: a green circle with a diagonal line, a red triangle with an exclamation mark, and six green circles labeled ON, PW, V1, V2, V3, and V4. To the right of these indicators are numerical values: 0.0%, 0.0Amp, 0.0Bar, 0.0SHK, and 0.0EV%. Below these values is a red line of text consisting of 15 hash symbols. At the bottom, there is a section labeled 'working hour' with a large zero in the center, flanked by upward and downward arrow icons.

Release 1.03 15-04-2020

CHANGES:

- Aligned with PLC application 2.7.3
- Removed Wizard Page
- Added Alarm detail for inverter errors

Release 1.02 03-04-2020

CHANGES:

- Aligned with PLC application 2.7.2
- Compiled for Free Studio Plus 1.2
- New Bios 659.7

Release 1.01 17-02-2020

CHANGES:

- Changed ON/OFF Icons Animation
- Fixed visualization issue.
- Added option to disable master communication in order to USE RS485 as slave to upgrade the HMITouch via RS485.

Release 1.00 12-02-2020

CHANGES: First Release

- 1- Added optimized Alarm Management
- 2- Added Compressor Form
- 3- Added FAN Form
- 4- Added IO Form
- 5- Added LOG Form
- 6- Added Bios settings Form

Quick Start guide

Enter in the key logo and enter the installer password "1".

The gear icon will appear and You will be able to enter in the service menu.

